GlideinWMS - Bug #5148

Factory RPM /etc/init.d/gwms-factory script does not work

01/06/2014 09:40 AM - Parag Mhashilkar

Status: Closed Start date: 01/06/2014

Priority: Normal Due date:

Assignee: Marco Mambelli % Done: 0%

Category:RPM - Frontend/FactoryEstimated time:0.00 hourTarget version:v3_2_4Spent time:0.00 hour

First Occurred: Stakeholders:

First Occurred.

Occurs In: Description

The script we provide with the gwms-factory rpm is bugged and options other than start/stop/upgrade/update may not be working correctly. We need to test and fix all the other options.

[root@cmssrv160 work-dir]# service gwms-factory down CMS_T1_US_FNAL_ce4Setting downtime...COMMAND: manageFactoryDowntimes.py -cmd down -dir /var/lib/gwms-factory/work-dir down down CMS_T1_US_FNAL_ce4

Usage:

```
manageFactoryDowntimes.py -dir factory_dir -entry ['all'|'factory'|'entries'|entry_name] -cmd [c
ommand] [options]
```

where command is one of:

```
add - Add a scheduled downtime period down - Put the factory down now(+delay) up - Get the factory back up now(+delay) ress - Set the up/down based on RESS status bdii - Set the up/down based on bdii status
```

ress+bdii - Set the up/down based both on RESS and bdii status check - Report if the factory is in downtime now(+delay)

 $\hbox{\tt vacuum} \qquad \hbox{\tt - Remove all expired downtime info}$

Other options:

```
-start [[[YYYY-]MM-]DD-]HH:MM[:SS] (start time for adding a downtime)
-end [[[YYYY-]MM-]DD-]HH:MM[:SS] (end time for adding a downtime)
```

-delay [HHh] [MMm] [SS[s]] (delay a downtime for down, up, and check cmds)
-ISinfo 'CEStatus' (attribute used in ress/bdii for creating downtimes)
-security SECURITY_CLASS (restricts a downtime to users of that security class)

(If not specified, the downtime is for all users.)

[FAILED]

-frontend SECURITY_NAME (Limits a downtime to one frontend)

-comment "Comment here" (user comment for the downtime. Not used by WMS.)

-cmd -dir and -entry arguments are required.

[root@cmssrv160 work-dir]#

History

#1 - 01/06/2014 10:42 AM - Krista Larson

Also, why is the factory_startup script in the working dir? It can't be used for anything.

#2 - 01/15/2014 10:36 AM - Parag Mhashilkar

I think this is also a good opportunity to modify the rpms to use init.d scripts that we ship with glideinwms.

#3 - 02/12/2014 10:03 AM - Marco Mambelli

- Assignee changed from Parag Mhashilkar to Marco Mambelli

#4 - 03/17/2014 03:08 PM - Marco Mambelli

Handling this in 5071

#5 - 03/24/2014 01:10 PM - Marco Mambelli

01/17/2021 1/2

The following commands are supposed to work:

gwms-factory {down|up} -entry factory|entries|ENTRY_NAME [-delay DELAY] [-frontend SEC_NAME|All] [-security SE
C_CLASS|All] [-comment COMMENT]
 gwms-factory infosysdown [-delay DELAY] [-frontend SEC_NAME] [-security SEC_CLASS|All] [-comment COMMENT]

gwms-factory statusdown -entry factory|entries|ENTRY_NAME [-delay DELAY]

I will test them once 5071 is merged

The other options mentioned above are not passed from the init script. Should support for those options be added? Thanks, Marco

#6 - 04/02/2014 04:10 PM - Marco Mambelli

- Status changed from New to Closed

See 5071 for details. Merged in branch_v3_2, ready for v3_2_4rc1 release

01/17/2021 2/2